

VIVOTEK NETWORK DEVELOPMENT PLATFORM

Data Packet Parser Version 5.1.0.3 2009/8/31

© 2009 VIVOTEK Inc. All Right Reserved

VIVOTEK may make changes to specifications and product descriptions at any time, without notice.

The following is trademarks of VIVOTEK Inc., and may be used to identify VIVOTEK products only: VIVOTEK. Other product and company names contained herein may be trademarks of their respective owners.

No part of this publication may be reproduced or utilized in any form or by any means, electronic or mechanical, including photocopying and microfilm, without permission in writing from VIVOTEK Inc.

TABLE OF CONTENTS

1.Overview	
1.1.Introduction	3
File Structure	3
2.SAMPLE CODE	
2.1. SaveAndLoadV3Packet	4
3.API Reference	
3.1.Data Structure	9
TMediaDataPacketInfo	10
TMediaDataPacketInfoV3	13
TMediaDataPacketInfoEx	14
TMediaPacketFirstReserved	15
TVUExtInfo	16
TMotionTriggerInfo	17
TMotionTriggerInfo TCaptureWinInfo	18
TMediaPacketTimeZoneInfo	
TMediaAudioInfo	20
3.2. Enumeration	
EMediaCodecType	
TMediaDBFrameType	24
3.3.API Definition	25
DataPacket_Parse	26
DataPacket_ParseV3	27
DataPacket GetEveryAudioInfo	28

1. Overview

1.1. Introduction

This document describes the properties and methods supported by the VIVOTEK Data Packet parser.

The Data Packet parser provides functions to parse and get the content of a Data Packet.

File Structure

DESCRIPTION			
doc\VNDP DataPacketParser API.pdf This manual			
Dynamic linking			
Dynamic runtime library			
Data Packet definition header file			
Data Packet parser header file			

2. SAMPLE CODE

2.1. SaveAndLoadV3Packet

DESCRIPTION

User may want to save and load the TMediaDataPacketInfoV3, but the structure of TMediaDataPacketInfoV3 is more complex than TMediaDataPacketInfo. Here we will introduce you how to save the packet into file and than re-load it from file.

SAMPLE CODE

Save Packet

```
DWORD dwDummyData = 0; // NOTE: for buffer is null
// STEP 1: write out pbyTLVExt
if (ptPacket->tlfEx.tRv1.tExt.pbyTLVExt != NULL)
{
  fwrite(ptPacket->tlfEx.tRv1.tExt.pbyTLVExt, 1, ptPacket->tlfEx.tRv1.tExt.dwTLVExtLen, fp);
}
else
  fwrite(&dwDummyData, 1, sizeof(dwDummyData), fp);
}
// STEP 2: write out pbyBuff
if (ptPacket->tlfEx.tlnfo.pbyBuff != NULL)
  fwrite(ptPacket->tlfEx.tlnfo.pbyBuff, 1, ptPacket->tlfEx.tlnfo.dwOffset + ptPacket->tlfEx.
tInfo.dwBitstreamSize, fp);
}
else
{
  fwrite(&dwDummyData, 1, sizeof(dwDummyData), fp);
}
// STEP 3: write out pbyVExtBuf
if (ptPacket->pbyVExtBuf != NULL)
  fwrite(&ptPacket->dwVExtLen, 1, sizeof(DWORD), fp);
  fwrite(ptPacket->pbyVExtBuf, 1, ptPacket->dwVExtLen, fp);
else
  fwrite(&dwDummyData, 1, sizeof(dwDummyData), fp);
}
```

Load Packet

```
// STEP 1: initial packet
memset(ptPacket, 0, sizeof(<u>TMediaDataPacketInfoV3</u>));
ptPacket->tlfEx.tRv1.tExt.dwStructSize = sizeof(TMediaDataPacketInfoV3);
// STEP 2: read into pbyTLVExt
fread(&ptPacket->tlfEx.tRv1.tExt.dwTLVExtLen, 1, sizeof(DWORD), fp);
if (ptPacket->tIfEx.tRv1.tExt.dwTLVExtLen != 0)
{
  memcpy(pbyTLVExt, &ptPacket->tlfEx.tRv1.tExt.dwTLVExtLen, sizeof(DWORD));
  ptPacket->tlfEx.tRv1.tExt.dwTLVExtLen = HTONL(ptPacket->tlfEx.tRv1.tExt.dwTLVExtLen);
  fread(pbyTLVExt + sizeof(DWORD), 1, ptPacket->tlfEx.tRv1.tExt.dwTLVExtLen, fp);
  ptPacket->tIfEx.tRv1.tExt.pbyTLVExt = pbyTLVExt;
}
ptPacket->tlfEx.tRv1.tExt.dwTLVExtLen += sizeof(DWORD);
// STEP 3: read into pbyBuff
DWORD dwFrameSize = 0;
fread(&dwFrameSize, 1, sizeof(DWORD), fp);
if (dwFrameSize != 0)
{
  memcpy(pbyBuff, &dwFrameSize, sizeof(DWORD));
  dwFrameSize = HTONL(dwFrameSize);
  fread(pbyBuff + sizeof(DWORD), 1, dwFrameSize, fp);
  ptPacket->tlfEx.tlnfo.pbyBuff = pbyBuff;
```

// STEP 4: read into pbyVExtBuf

```
DWORD dwVExtLen = 0;
fread(&dwVExtLen, 1, sizeof(DWORD), fp);
if (dwVExtLen)
{
    dwVExtLen = HTONL(dwVExtLen);
    fread(pbyVExtBuf, 1, dwVExtLen, fp);
    ptPacket->pbyVExtBuf = pbyVExtBuf;
}
```

// STEP 5: reconstruct packet

DataPacket_ParseV3(ptPacket);

TIPS

Remember to set ptPacket->tIfEx.tRv1.tExt.dwStructSize = sizeof(<u>TMediaDataPacketInfoV3</u>), otherwise the DataPacket_ParseV3 function won't parse the V3 information.

3. API Reference

This chapter contains the API function calls for the Data Packet Parser.

3.1. Data Structure

The data structure is depicted here.



TMediaDataPacketInfo

This structure provides the information in the Data Packet.

typedef struct BYTE *pbyBuff; **DWORD** dwOffset; DWORD dwBitstreamSize; **DWORD** dwStreamType; **DWORD** dwFrameNumber; TMediaDBFrameType tFrameType; **DWORD** dwFirstUnitSecond; **DWORD** dwFirstUnitMilliSecond; **BOOL** bFixedFrameSize: DWORD dwAudioSamplingFreq; **BYTE** byAudioChannelNum; **DWORD** dwDIAlert; **DWORD** dwDO: BOOL bMotionDetection[3]; bMotionDetectionAlertFlag[3]; BOOL **BYTE** byMotionDetectionPercent[3]; WORD wMotionDetectionAxis[3][4]; **BOOL** bTimeModified: BOOL bAudioDI; BOOL bNoVideoSignal; TMediaDataPacketInfo;

Members

*pbyBuff

the pointer of buffer containing this Data Packet

dwOffset

the offset of buffer refer to the media bitstream, 32-bits align

dwBitstreamSize

the size of media bitstream

dwStreamType

the type of stream in the Data Packet, indicated by enumeration EMediaCodecType

dwFrameNumber

the number of frame in the Data Packet

tFrameType

the type of frame

dwFirstUnitSecond

the second of first frame in the Data Packet (time in seconds from midnight, January 1, 1970)

dwFirstUnitMilliSecond

the millisecond of first frame in the Data Packet

bFixedFrameSize

the flag indicates the frame size is fixed

dwAudioSamplingFreq

audio sampling frequency, if the stream has only one kind of sampling frequency, this field is ignored.

byAudioChannelNum

the channel number of audio, if the stream has only one kind of channel number, this field is ignored.

dwDIAlert

the digital input alert, each bit presents a digital input source. Bit 0 is for DI 0, bit 1 is for DI 1, bit 2 is for DI 2, and bit 3 is for ID 3. Other bits are reserved.

dwDO

Each bit is used to indicate the DO (H/L). It supports two digital output in the present. The LSB indicates the first digital output.

bMotionDetection[3]

the flags of motion detection which indicate the motion detection windows are active or not

bMotionDetectionAlertFlag[3]

the flags of motion detection alert

byMotionDetectionPercent[3]

the percentages of motion detection

wMotionDetectionAxis[3][4]

the window of motion detection, 1st element is the left coordinate of rectangular, 2nd element is the top coordinate of rectangular, 3rd element is the width of rectangular and 4th element is the height of rectangular.

bTimeModified

the flag indicates the time is modified according to timezone. If the value is FALSE, the time is dependent the time zone

bAudioDI

the flag indicates audio packets take the DI Alert information

bNoVideoSignal

the flag indicates the loss of video signal

Remarks

Variable "dwDIMask" is removed in version 2.0.0.0. Variable "dwDO" is added in version 3.0.0.0. Variable "bTimeModified" and "bAudioDI" are added in version 4.0.0.0. Variable "bNoVideoSignal" is added in version 5.0.0.0.

Requirements

TMediaDataPacketInfoV3

This structure provides the information in the new Data Packet (version 3). The most important part of the V3 is the capturing and cropping information, you could refer to the sample code "GetV3Information" for the detail.

typedef struct
{
TMediaDataPacketInfoEx

<u>TMediaDataPacketInfoEx</u> tIfEX; <u>TMediaPacketTimeZoneInfo</u> tTZ;

DWORD dwUTCTime;

TVUExtInfo tVUExt;

BYTE *pbyVExtBuf;
DWORD dwVExtLen

} TMediaDataPacketInfoV3;

Members

tlfEx

TMediaDataPacketInfoEx

tTZ

TMediaPacktTimeZoneInfo

dwUTCTime:

The UTC time of this packet. This value could be got from dwFristUnitSecond and time zone information, too.

tVUExt

TVUExtInfo

pbyVExtBuf

Video further extension. If the value is null, it means this packet don't have such extension.

dwVExtLen

The size of the pbyVExtBuf.

Requirements

TMediaDataPacketInfoEx

This structure provides the information in the Data Packet.

typedef struct **TMediaDataPacketInfo** tInfo: UMediaPktReserved1 tRv1; **DWORD** dwWidth; **DWORD** dwHeight; **DWORD** dwWidthPadLeft **DWORD** dwWidthPadRight **DWORD** dwHeightPadTop **DWORD** dwHeightPadBottom } TMediaDataPacketInfoEx;

Members

tInfo

TMediaDataPacketInfo

tRv1

UMediaPktReserved1. It is a union of <u>TMediaPacketFirstReserved(tExt)</u> and void*(apvReserved[4]). In most case, we use the tExt field.

For example:PacketV3.tlfEx.tRv1.tExt.pbyTLVExt

dwWidth

The width of the video frame if it's video (includes padding if any)

dwHeight

The height of the video frame if it's video (includes padding if any)

dwWidthPadLeft

Padded width of left, the value is usually zero.

dwWidthPadRight

Padded width of right, the value is usually zero.

dwHeightPadTop

Padded height of top, the value is usually zero.

dwHeightPadBottom

Padded height of bottom, the value is usually zero.

Requirements

TMediaPacketFirstReserved

This structure provides the information of extension data of a frame

Members

pbyTLVExt

The pointer to the tag/length/data extension of a frame. The pointer would point to the location after media data in pbyBuff

dwTLVExtLen

the length of the pbyTLVExt

dwStructureSize

the size of the structure. If this is 0, it means the packet is Ex only, else this maps the size of the overall packet structure

Requirements

TVUExtInfo

This structure provides the information in the Video Extension.

typedef struct

DWORD dwPIR;
DWORD dwWLLed;

TCaptureWinInfo tCapWinInfo;

DWORD dwTamperingAlert;

<u>TMotionTriggerInfo</u> *ptMTI;

} TMediaDataPacketInfoEx;

Members

dwPIR

the PIR status, HIGH word means the PIR enabled flag, LOW word contains the values.

dwWLLed

the status for white light LED

tCapWinInfo

the capture window info

dwTamperingAlert

tamperingalert info

*ptMTI

point to the data in TMediaDataPacketInfo

Requirements

TMotionTriggerInfo

This structure provides the information of motion window. All the value is the same as the value in TMediaDataPacketInfo.

typedef struct {		
BOOL	bMotionDetection[3];	
BOOL	bMotionDetectionAlertFlag[3];	
BYTE	byMotionDetectionPercent[3];	
WORD	wMotionDetectionAxis[3][4];	
} TMotionTriggerInfo;	_	

Members

bMotionDetection[3]

the flags of motion detection which indicate the motion detection windows are active or not

bMotionDetectionAlertFlag[3]

the flags of motion detection alert

byMotionDetectionPercent[3]

the percentages of motion detection

wMotionDetectionAxis[3][4]

the window of motion detection, 1st element is the left coordinate of rectangular, 2nd element is the top coordinate of rectangular, 3rd element is the width of rectangular and 4th element is the height of rectangular.

Requirements

TCaptureWinInfo

This structure provides the information of Capture Window

typedef struct {		
BOOL	bWithInfo;	
WORD	wCapW;	
WORD	wCapH;	
WORD	wOffX;	
WORD	wOffY;	
WORD	wCropW;	
WORD	wCropH;	
<pre>} TCaptureWinInfo;</pre>		

Members

bWithInfo

If the information is valid.

wCapW

Capture Width

wCapH

Capture Height

wOffX

Offset X

wOffY

Offset Y

wCropW

Cropping Width

wCropH

Cropping Height

Requirements

TMediaPacketTimeZoneInfo

This structure provides the information of time zone and daylight saving.

typedef struct
{
BOOL bTimeZone;
long IDLSaving;
long IOffsetSeconds;
} TMediaPacketTimeZoneInfo;

Members

bTimeZone

if the packet contains time zone information, if no, the following fields are from client machine

IDLSaving

the daylight saving time in seconds (if 0 it means no day-light saving), -3600 for most case

IOffsetSeconds

offset of seconds from GMT time; for example Taipei will be 8 * 3600 = 28800

Requirements

TMediaAudioInfo

This structure is used to get the size of audio units in a Data Packet through the DataPacket_GetEveryAudioInfo function.

typedef struct
{
DWORD dwSize;
} TMediaAudioInfo;

Members

dwSize

the size of an audio unit

Remarks

Requirements

parsedatapacket.h

3.2. Enumeration

The enumeration used is depicted here.



EMediaCodecType

This enumeration indicates the media codec type.

```
typedef enum
mctJPEG
                      = 0x0001,
mctH263
                      = 0x0002,
mctMP4V
                      = 0x0004,
mctH264
                      = 0x0008,
mctG7221
                      = 0x0100,
mctG729A
                      = 0x0200,
mctAAC
                      = 0x0400,
mctGAMR
                      = 0x0800,
                      = 0x1000
mctSAMR
} EMediaCodecType;
```

Values

mctJPEG

the codec type is JPEG (image, video)

mctH263

the codec type is H.263 (video)

mctMP4V

the codec type is MPEG-4 video (video)

mctH264

the codec type is H.264 video (video)

mctG7221

the codec type is G.722.1 (audio)

mctG729A

the codec type is G.729A (audio)

mctAAC

the codec type is AAC (audio)

mctGAMR

the codec type is AMR (audio)

mctSAMR

the codec type is SAMR (audio)

Remarks

Requirements

mediatypedef.h



TMediaDBFrameType

This enumeration indicates the frame type of media.

typedef enum {		
MEDIADB_FRAME_INTRA	= 0,	
MEDIADB_FRAME_PRED	= 1,	
MEDIADB_FRAME_BIPRED } TMediaDBFrameType;	= 2	

Values

MEDIADB_FRAME_INTRA

the intra frame

MEDIADB_FRAME_PRED

the prediction frame

MEDIADB_FRAME_BIDIR

the bi-direction prediction frame

Remarks

Requirements

mediatypedef.h

3.3. API Definition

The API definition is depicted here.



DataPacket_Parse

Parse the Data Packet in the input buffer.

Syntax

SCODE DataPacket_Parse (<u>TMediaDataPacketInfo</u> *ptDataPacketInfo);

Parameters

*ptDataPacketInfo

[in/out] A pointer of data structure storing information of Data Packet

Return Values

S OK

Parse Data Packet successfully.

S FAIL

Parse Data Packet failed.

Remarks

Before calling this function, the field of pbyBuff in the Data Packet structure must be valid.

Requirements

parsedatapacket.h

See Also

DataPacket_ParseV3

Parse the Data Packet in the input buffer into TMediaDataPacketInfoV3.

Syntax

SCODE DataPacket ParseV3 (TMediaDataPacketInfoV3 *ptDataPacketInfo

Parameters

*ptDataPacketInfoV3

[in/out] A pointer of data structure storing information of Data Packet

Return Values

S OK

Parse Data Packet successfully.

S_FAIL

Parse Data Packet failed.

Remarks

The usage of <u>DataPacket_ParseV3</u> is more complex than <u>DataPacket_Parser</u>, please refer to the sample code "SaveAndLoadV3Packet" for the usage.

Requirements

parsedatapacket.h

See Also

DataPacket_GetEveryAudioInfo

This function gets the size and buffer address of every audio unit in a Data Packet.

Syntax

SCODE DataPacket_GetEveryAudioInfo

BYTE *pbyInBuf,

TMediaAudioInfo *ptAudioInfo);

Parameters

pbyInBuf

[in] the pointer of buffer containing an audio Data Packet

ptAudioInfo

[out] the pointer of structure to store the list of audio information, the size must be larger than audionumber * sizeof(<u>TMediaAudioInfo</u>)

Return Values

S OK

Get audio info successfully.

S_FAIL

Get audio info failed.

Remarks

Requirements

parsedatapacket.h

See Also