



Arecont Vision

AV SDK

Interface and Usage Description

Rev 2.8.2

April 5, 2010

support@arecontvision.com

AV SDK AND ASSOCIATED FILES ARE PROVIDED FOR CUSTOMER CONVENIENCE ON AS-IS BASIS. ARECONT VISION, LLC DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS. IN NO EVENT SHALL ARECONT VISION BE LIABLE FOR ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTUOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

Package Contents	3
Introduction	3
AV2000Types.h	3
Data Types.....	3
Errors	11
Error Handling Example.....	11
Error Codes defined in AVErrCodes.h	11
AV2000SDK.dll and AV2000SDK.so	13
List of Functions.....	13
Camera Communication Functions	15
Memory Allocation.....	20
Camera Detection and IP Configuration Functions	22
Auto-Iris Functions.....	22
DayNight Functions.....	22
CopyRight Strings Functions.....	22
Motion Detection	23
Binning Mode.....	26
1080p Mode.....	26
Single Capture Mode.....	26
Auxiliary IO Functions	27
Panoramic Camera Functions	29
Examples	31
DLL Usage Notes	31
Typical Usage	31
Multi-Threaded Applications.....	31
Miscellaneous	32
Maximum Image Sizes That can be Specified for AV Cameras.....	32
Revision History.....	32

Package Contents

File Name	Description
AV2000SDK.dll	Windows shared library. Provides means of access to functions of Arecont Vision cameras from within user applications.
AV2000SDK.so	Linux shared library, verified with Redhat Linux v4.6
AV2000Types.h	Declares data types used in conjunction with AV SDK
AVLoadDll.cpp	Example of loading SDK dll
AVIntegrationExample	Demo program, MS VC++, download from Arecont Vision website
AVErrorCodes.h	Error code names
AV_SDK_v*.pdf	This file

Introduction

AV SDK is a collection of libraries and examples to connect and capture images from Arecont Vision cameras. SDK supports Windows and Linux platforms.

In the text below, a “client” is defined as the object created in the DLL that handles communication with the camera.

AV2000Types.h

Data Types

- ```
enum EXIF_STRING_ID {CAMERA_MAKE_STRING = 0 , CAMERA_MODEL_STRING,
SOFTWARE_STRING, COPYRIGHT_STRING};
```

CAMERA\_MAKE\_STRING is used to specify the name of camera manufacturer.  
CAMERA\_MODEL\_STRING is used to specify camera model.  
CAMERA\_SOFTWARE\_STRING is used to specify the name of software that uses this SDK.  
COPYRIGHT\_STRING is used to specify copy right owner of the image generated by this SDK.  
\*\*These strings will be embedded into the header of every JPEG image generated by this SDK in form of EXIF (EXchangeable Image File format, a standard of Japan Electronics and Information Technology Industries Association).  
\*\*EXIF is supported by Microsoft Windows. In Windows these information will be displayed in right-click menu\properties\summary (advanced).
- ```
enum IMAGE_RESOLUTION { imFULL = 1, imHALF = 2, imZOOM };
```

imHALF is used to request images decimated by a factor of 2 in both directions, (e.g AV2100 decimated image size is 800x600);
imFULL is used to request an entire frame;
imZOOM – is used to request image window (a portion of the image)
- ```
enum CodecID {JPEG_CODEC = 0 , H264_CODEC = 1};
```

CodecID is used in function **GetWindowImageQEx** to specify the way image encoder type in camera.  
JPEG\_CODEC – corresponds to MJPEG encoder.  
H264\_CODEC - corresponds to H.264 encoder.

```

• enum CAMERA_PARAMETER { cpBRIGHTNESS, cpSATURATION, cpSHARPNESS,
cpBLUE, cpRED, cpILLUMINATION, cpLIGHTING, cpCAMERA_MODE,
cpSHORT_EXPOSURES, cpQUALITY_FULL, cpQUALITY_HALF, cpQUALITY_ZOOM,
cpDOUBLESCAN, cpROLL, cpIRIS_ENABLED, cpIRIS_SPEED, cpIRIS_GAIN,
cpIRIS_PEROSITION_ENABLED, cpIRIS_REPOSITION_F_STOPS,
cpIRIS_REPOSITION_F_STOPS_MIN, cpIRIS_REPOSITION_PERIOD,
cpIRIS_REPOSITION_STABLE_PERIOD, cpDAY_NIGHT_MODE,
cpDAY_NIGHT_TRIGGER_NIGHT, cpDAY_NIGHT_TRIGGER_DAY, cpEXPOSURE_MODE,
cpEXPOSURE_WINDOW_LEFT, cpEXPOSURE_WINDOW_TOP, cpEXPOSURE_WINDOW_WIDTH,
cpEXPOSURE_WINDOW_HEIGHT, cpSENSOR_LEFT, cpSENSOR_TOP, cpSENSOR_WIDTH,
cpSENSOR_HEIGHT, cpSENSOR_BLACK_WHITE_LEFT,
cpSENSOR_BLACK_WHITE_TOP, cpSENSOR_BLACK_WHITE_WIDTH,
cpREQUEST_WIDTH, cpREQUEST_HEIGHT, cpREQUEST_LEFT, cpREQUEST_TOP,
cpREQUEST_WIDTH, cpREQUEST_HEIGHT, cpQUALITY, cpRESOLUTION,
cpPER_CENT_IMAGE_RECTANGLE, cpREQUESTED_BLOCK_SIZE, cpMD_ENABLED,
cpMD_MODE, cpMD_LEVEL_THRESH, cpMD_TOTAL_ZONES, cpMD_ZONE_SIZE,
cpMD_EXPLOSURE_SENSITIVITY, cpMD_MATRIX, cpMD_DETAIL, cpH264,
cpBIT_RATE, cpGAMMA, cpBIN_DAY, cpBIN_NIGHT, cpBIN_1080P }

```

| Parameter         | Description                                                                                                                                                                                                                                                                                                                             | Values                      | Default <sup>1</sup> | Stored           |
|-------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------------------------|----------------------|------------------|
| cpBRIGHTNESS      | Sets target image brightness                                                                                                                                                                                                                                                                                                            | -99... 99                   | 5                    | Camera           |
| cpSATURATION      | Color saturation, % of normal saturation                                                                                                                                                                                                                                                                                                | 0, 25, 37, 50, 75, 100, 125 | 100                  | Camera           |
| cpSHARPNESS       | Image sharpening                                                                                                                                                                                                                                                                                                                        | 0..4                        | 2                    | Camera           |
| cpBLUE            | Blue AWB target                                                                                                                                                                                                                                                                                                                         | -10..10                     | 0                    | Camera           |
| cpRED             | Red AWB target                                                                                                                                                                                                                                                                                                                          | -10..10                     | 0                    | Camera           |
| cpILLUMINATION    | 0 – auto<br>1 – indoor illumination<br>2 – outdoor illumination<br>3 – mixed illumination                                                                                                                                                                                                                                               | 0..3                        | 0                    | Camera           |
| cpLIGHTING        | Power supply frequency, 50 or 60Hz                                                                                                                                                                                                                                                                                                      | 50 or 60                    | 50                   | Camera           |
| cpCAMERA_MODE     | Determines low-light camera operation<br>0 – maintain higher frame rate<br>1 – higher image quality<br>2 – balanced<br>3 – custom mode (read only value, to set use SetCustomMode)<br>4 – HIGH_SPEED mode - fixed shutter widths (set by cpSHORT_EXPOSURES)<br>5 – MoonLight™ mode – long exposures with proprietary noise cancellation | 0..5                        | 0                    | Camera           |
| cpSHORT_EXPOSURES | Sets fixed shutter width in ms; Only valid with cpCAMERA_MODE = 4                                                                                                                                                                                                                                                                       | 1...80                      | 5                    | Camera           |
| cpQUALITY_FULL    | JPEG compression quality in imFULL mode. Higher value corresponds to higher quality                                                                                                                                                                                                                                                     | 1..21                       | 15                   | DLL <sup>2</sup> |

<sup>1</sup> Some defaults are stored in the camera's non-volatile memory and may become different from the ones shown in the table.

<sup>2</sup> If camera-stored jpeg quality setting is required, use cpQUALITY with GetDefaultImage

| Parameter               | Description                                                                                                                                                                                                                                                                                             | Values                                      | Default             | Stored           |
|-------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------------------------------------|---------------------|------------------|
| cpQUALITY_HALF          | JPEG compression quality in imHALF                                                                                                                                                                                                                                                                      | 1..21                                       | 15                  | DLL <sup>2</sup> |
| cpQUALITY_ZOOM          | Compression quality in imZOOM mode                                                                                                                                                                                                                                                                      | 1..21                                       | 15                  | DLL <sup>2</sup> |
| cpDOUBLESCAN            | 0 – requesting an image from a camera will obtain a newly captured image. The camera will delay its response until the new image is captured<br>1 – the camera will output last buffered image if the new image is not yet available. Use this mode to request multiple sub-windows from the same image | 0, 1                                        | 0                   | DLL              |
| cpREQUESTED_BLOCK_SIZE  | Allows the user to specify whether camera should transmit images via single part TFTP packets (1450 bytes) or multi-part TFTP packets (2904 bytes); Valid for firmware versions 52109 or above;                                                                                                         | 1450, 2904                                  | 2904                | Camera           |
| cpROLL                  | 180 – rotate image by 180 degrees. Use this mode if the camera is mounted upside-down                                                                                                                                                                                                                   | 0, 180                                      | 0                   | Camera           |
| cpEXPOSURE_MODE         | Controls auto backlight compensation and automatic vs. user-defined exposure measurement window;<br>0 – automatic mode without backlight compensation<br>1 – automatic mode with backlight compensation<br>2 – user-controlled exposure window without backlight compensation                           | 0,1,2                                       | 1                   | Camera           |
| cpEXPOSURE_WINDOW_LEFT  | Left coordinate of user-defined auto-exposure measurement window. Valid then cpEXPOSURE_MODE = 2                                                                                                                                                                                                        | Larger than cpSENSOR_LEFT                   | 32                  | Camera           |
| cpEXPOSURE_WINDOW_TOP   | Top coordinate of user-defined auto-exposure measurement window. Valid then cpEXPOSURE_MODE = 2                                                                                                                                                                                                         | Larger than cpSENSOR_TOP                    | 32                  | Camera           |
| cpEXPOSURE_WINDOW_WIDTH | Width of user-defined auto-exposure measurement window. Valid then cpEXPOSURE_MODE = 2                                                                                                                                                                                                                  | Smaller than cpSENSOR_WIDTH – cpSENSOR_LEFT | cpSENSOR_WIDTH – 64 | Camera           |

| Parameter                | Description                                                                             | Values                                      | Default                                                                           | Stored |
|--------------------------|-----------------------------------------------------------------------------------------|---------------------------------------------|-----------------------------------------------------------------------------------|--------|
| cpEXPOSURE_WINDOW_HEIGHT | Height of user-defined auto-exposure measurement window. Valid then cpEXPOSURE_MODE = 2 | Smaller than cpSENSOR_HEIGHT - cpSENSOR_TOP | cpSENSOR_HEIGHT - 64                                                              | Camera |
| cpSENSOR_LEFT            | Left coordinate of sensor window                                                        | Up to sensor width                          | 0                                                                                 | Camera |
| cpSENSOR_TOP             | Top coordinate of sensor window                                                         | Up to sensor height                         | 0                                                                                 | Camera |
| cpSENSOR_WIDTH           | Width of sensor window                                                                  | 320 ... up to sensor width                  | Model-dependent<br>See Table 1                                                    | Camera |
| cpSENSOR_HEIGHT          | Height of sensor window                                                                 | 240 ... up to sensor height                 | Model-dependent<br>See Table 1                                                    | Camera |
| cpWIDTH                  | Image width returned by functions GetImage and GetImage2                                | Up to cpSENSOR_WIDTH                        | AV1300 - 1280<br>AV2100 - 1600<br>AV3100 - 1920<br>AV5100 - 2560<br>AV3130 - 1920 | SDK    |
| cpHEIGHT                 | Image height returned by functions GetImage and GetImage2                               | Up to cpSENSOR_HEIGHT                       | AV1300 - 1024<br>AV2100 - 1200<br>AV3100 - 1200<br>AV5100 - 1600<br>AV3130 - 1200 | SDK    |
| cpREQUEST_LEFT           | Default image left coordinate relative to sensor window for GetDefaultImage().          | Up to sensor width                          | 0                                                                                 | Camera |
| cpREQUEST_TOP            | Default image top coordinate relative to sensor window for GetDefaultImage().           | Up to sensor height                         | 0                                                                                 | Camera |
| cpREQUEST_WIDTH          | Default image width for GetDefaultImage().                                              | 320 ... up to sensor width                  | Default cpSENSOR_WIDTH                                                            | Camera |
| cpREQUEST_HEIGHT         | Default image height for GetDefaultImage().                                             | 240 ... up to sensor height                 | Default cpSENSOR_HEIGHT                                                           | Camera |
| cpQUALITY                | Default image quality for GetDefaultImage()                                             | 1...20                                      | 15                                                                                | Camera |
| cpRESOLUTION             | Default image resolution for GetDefaultImage()                                          | Full, half (0,1)                            | 1                                                                                 | Camera |
| cpH264                   | Use it to find out if H.264 encoder enable or not.                                      | 0 - disable<br>0> - enable                  | Depends on the model                                                              | SDK    |
| cpAUTO_EXPOSITION        | 0 - disable (freeze) auto-exposure<br>1 - enable auto-exposure                          | 0,1                                         | Always 1 after reset                                                              | n/a    |
| cpGAMMA                  | Round(100/gamma)                                                                        | 40..100<br>gamma2.5~1.0                     | 60<br>gamma=1.67                                                                  | Camera |

| Parameter                                                | Description                                                                                                                                                                                          | Values                       | Default                                                 | Stored |
|----------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|------------------------------|---------------------------------------------------------|--------|
| <b>AV10005 Dual-mode Camera Specific Parameters</b>      |                                                                                                                                                                                                      |                              |                                                         |        |
| cpBIN_DAY                                                | Binning in Day mode                                                                                                                                                                                  | 0,1                          | 0                                                       | Camera |
| cpBIN_NIGHT                                              | Binning in Night mode                                                                                                                                                                                | 0,1                          | 1                                                       | Camera |
| cpBIN_1080P                                              | 1080p mode                                                                                                                                                                                           | 0,1                          | 0                                                       | Camera |
| <b>On-Camera Motion-Detection Parameters<sup>3</sup></b> |                                                                                                                                                                                                      |                              |                                                         |        |
| cpMD_ENABLED                                             | Enables detection<br>'0' – disabled<br>'1' – enabled                                                                                                                                                 | 0,1                          | 0                                                       | Camera |
| cpMD_MODE                                                | Motion detection mode<br>'1' – camera returns the image of zero length in the absence of motion;<br>'0' – camera always returns requested image                                                      | 0,1                          | 0                                                       | Camera |
| cpMD_LEVEL_THRESH                                        | Motion threshold (sensitivity to change)                                                                                                                                                             | 2..255                       | 3                                                       | Camera |
| cpMD_TOTAL_ZONES                                         | Number of independent motion detection zones;<br>Currently must be 64.<br>There are 8 rows of zones, 8 zones per row                                                                                 | 64                           | 64                                                      | Camera |
| cpMD_ZONE_SIZE                                           | Size of motion detection zones measured in number of 32x32 pixel blocks in each zone; All zones are squares of the same size from 7x7 to 15x15                                                       | 7..15<br>(8...15 for AV3100) | 8                                                       | Camera |
| cpMD_EXPLOSURE_SENSITIVITY                               | Sensitivity to overall brightness changes. If more than this number of zones have motion it is assumed that the change is due to illumination change and detected motion is ignored;                 | 0..64                        | 40 for AV3100<br><br>30 for AV2100<br><br>20 for AV1300 | Camera |
| cpMD_MATRIX                                              | Privacy matrix. 8-byte array, where each byte corresponds to one row of motion detection zones. Each bit in a byte enables motion detection in a corresponding zone, if set to '1'. Leftmost zone is |                              | All '1'                                                 | Camera |

<sup>3</sup> By the time of this manual, on-camera motion detection is available on all AV cameras including AV8360, AV8180, AV8365 and AV8185. Some older models (for example old AV5100) require firmware/hardware upgrade to support on-camera motion detection.

| Parameter                                                             | Description                                                                                                                                                                                                 | Values                                 | Default              | Stored |
|-----------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------------------------------------|----------------------|--------|
|                                                                       | controlled by MSB, rightmost zone by LSB. Also see Motion Detection section. <sup>4</sup>                                                                                                                   |                                        |                      |        |
| cpMD_DETAIL                                                           | Allows to control the size of moving objects to be detected. The value is the number of 32x32 sub-zones within each zone that should contain motion for the entire zone to be considered to contain motion. | 1<br>through<br>square of<br>zone size | 1                    | Camera |
| <b>Auto-Iris Parameters<sup>5</sup></b>                               |                                                                                                                                                                                                             |                                        |                      |        |
| cpIRIS_ENABLED                                                        | Enable auto-iris<br>'0' – disabled<br>Non-zero value – enabled                                                                                                                                              | 0,non-zero                             | 0                    | Camera |
| cpIRIS_SPEED                                                          | Iris servo-loop gain. Always keep at default setting.                                                                                                                                                       | 1..255                                 | 64                   | Camera |
| cpIRIS_GAIN                                                           | Maximum gain to be used for exposure when auto-iris is enabled. Gain = x/8                                                                                                                                  | 8..255                                 | 20                   | Camera |
| cpIRIS_REPOSITION_F_STOPS                                             | Number of f-stops to close, in half-steps: $N[f\text{-stops}] = (x+1)/2$ .                                                                                                                                  | 1..15                                  | 5 <sup>6</sup>       | Camera |
| cpIRIS_REPOSITION_F_STOPS_MIN                                         | Minimum number of f-stops to close, in half-steps: $N[f\text{-stops}] = (x+1)/2$ .                                                                                                                          | 1..15                                  | 1                    | Camera |
| cpIRIS_REPOSITION_PERIOD                                              | Approximate time between repositioning.<br>$T[\text{minutes}] = x/20$                                                                                                                                       | 0..900                                 | 600 (2M)<br>500 (3M) | Camera |
| cpIRIS_REPOSITION_STABLE_PERIOD                                       | Approximate time to evaluate scene before closing the iris.<br>$T[\text{minutes}] = x/20$                                                                                                                   | 0..900                                 | 1                    | Camera |
| <b>Single Sensor and Panoramic DayNight model Specific Parameters</b> |                                                                                                                                                                                                             |                                        |                      |        |
| cpDAY_NIGHT_MODE                                                      | 0 = automatic<br>1 = day<br>2 = night                                                                                                                                                                       | 0,1,2                                  | Always 0 after reset | Camera |
| cpDAY_NIGHT_TRIGGER_NIGHT                                             | Gain threshold for switching from day mode to night mode                                                                                                                                                    | 64..512                                | 256                  | Camera |
| cpDAY_NIGHT_TRIGGER_DAY                                               | When brightness increase to $1 + 2^{(-x)}$ times the                                                                                                                                                        | 1..4                                   | 2                    | Camera |

<sup>4</sup> For detailed description of cpMD\_MATRIX usage reference Motion Detection section of this manual.

<sup>5</sup> Auto-iris parameters do not apply to AV3130

<sup>6</sup> This value depends on the model of the auto-iris lens



| Parameter                                                     | Description                                                                                                                                   | Values        | Default              | Stored |
|---------------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------|---------------|----------------------|--------|
|                                                               | darkest point, return to day mode.                                                                                                            |               |                      |        |
| <b>AV3130/AV3135 Day-Night Specific Parameters</b>            |                                                                                                                                               |               |                      |        |
| cpDAY_NIGHT_MODE                                              | AV3130/3135 mode:<br>- 0 = automatic<br>- 1 = day<br>- 2 = night                                                                              | 0,1,2         | Always 0 after reset | n/a    |
| cpDAY_NIGHT_TRIGGER_NIGHT                                     | AV3130/3135 exposure threshold to enter the night mode<br>$Fstops = 2^{(x / 2.0)}$                                                            | 0..18         | 3                    | Camera |
| cpDAY_NIGHT_TRIGGER_DAY                                       | AV3130/3135 hysteresis to return to day mode<br>$Fstops = 2^{(x / 2.0)}$                                                                      | 0..6          | 2                    | Camera |
| cpSENSOR_BLACK_WHITE_LEFT                                     | Left coordinate of monochrome sensor window                                                                                                   | Up to 1280    | 0                    | Camera |
| cpSENSOR_BLACK_WHITE_TOP                                      | Top coordinate of monochrome sensor window                                                                                                    | Up to 1024    | 0                    | Camera |
| cpSENSOR_BLACK_WHITE_WIDTH                                    | Width of monochrome sensor window                                                                                                             | Up to 1280    | 1280                 | Camera |
| cpSENSOR_BLACK_WHITE_HEIGHT                                   | Height of monochrome sensor window                                                                                                            | Up to 1024    | 800                  | Camera |
| cpPER_CENT_IMAGE_RECTANGLE                                    | If set, GetWindowImage parameters are specified as percentage of sensor window                                                                | 0,1           | 0                    | Camera |
| <b>Panoramic Specific Parameters (AV8360/8180/8365/8185 )</b> |                                                                                                                                               |               |                      |        |
| cpMS_NUMBER_OF_SENSOR                                         | Sensor (channel) selected for setting its parameters                                                                                          | 1,2,3,4       | 0                    | SDK    |
| cpMS_CHANNEL_ENABLE                                           | A 4-bit mask to select a combination of sensors (channels) that are enabled for sending images                                                | 0x0001-0x000F | 0x000F               | Camera |
| cpMS_FULL_RES_ENABLE                                          | A 4-bit mask to select a combination of sensors (channels) that send full resolution images; all other enabled channels send decimated images | 0x0000-0x000F | 0x0000               | Camera |
| cpMS_ZOOM_WIN_ENABLE                                          | A 4-bit mask to select a combination of sensors (channels) that send zoom window images                                                       | 0x0000-0x000F | 0x0000               | Camera |
| cpMS_ONE_SHOT_ENABLE                                          | A 4-bit mask to select a combination of sensors (channels) that send a                                                                        | 0x0000-0x000F | 0x0000               | Camera |

| Parameter      | Description                                                                                                                            | Values   | Default | Stored |
|----------------|----------------------------------------------------------------------------------------------------------------------------------------|----------|---------|--------|
|                | single full resolution image only once. To repeat, set the parameter again.                                                            |          |         |        |
| cpMS_IS_ZOOMED | Indicates whether the image received is a zoom window.                                                                                 | 0,1      | 0       | n/a    |
| cpMS_QUAD_MODE | Enables a special camera mode in which each channel sends a full resolution image followed by four decimated images from all channels. | 0,1      | 0       | Camera |
| cpBIT_RATE     | Desired bit rate for H.264 streams.                                                                                                    | 0..65000 | 0       | Camera |

In the table above some defaults are stored in the camera non-volatile memory. Other parameters apply to DLL and are lost when the program terminates and DLL is unloaded. The application programmer is responsible for saving these settings and setting them again the next time DLL is loaded.

**NOTE: Parameters described as stored on camera are updated in the camera non-volatile memory only AFTER THE CALL TO Permanently(). Mere writing a new value using SetAV200Parameter does not modify non-volatile memory. Permanently() function should NOT be called more than 20,000 times in a camera lifetime.**

```
struct AV2000Addr{
 unsigned char ip[4],
 mac[6];
}
```

This structure contains camera Ethernet MAC and associated IP.

```
enum IRIS_STATUS { irUNKNOWN = 0, irMANUAL, irDISABLED, irIDLE,
irEVALUATING, irEVALUATING_TOO_DARK, irCLOSING, irCLOSED, irOPENING };
```

```
irUNKNOWN – iris status cannot be determined
irMANUAL – iris operates in manual mode
irDISABLED – iris is disabled or iris cable is unplugged
irIDLE – iris is idle
irEVALUATING – camera is evaluating the scene before closing the iris
irEVALUATING_TOO_DARK – same as irEVALUATING, but previous evaluation concluded
that the scene is too dark to allow the iris to close
irCLOSING – the iris is closing down
irCLOSED – the iris is closed down
irOPENING – the iris is opening
```

## Errors

```
struct ClientError{
int code; char description[256];
};
```

The structure is used by AV client to communicate encountered errors, where

code – is the error code. Currently supported values are:

<0 – fatal error, caused by DLL code

=0 – error code is undefined.

The application should terminate when receiving an error code less or equal to 0, since DLL behavior may become unpredictable

>0 – recognized internal DLL error, typically caused by incorrect arguments passed to

DLL functions or a network communication error

description – ASCII error description.

Errors returned by the ClientError structure can originate either from OS system or from DLL code. System errors have a code and description defined by the operating system. Windows error codes can be found in MSDN documentation. <error.h> defines Linux errors.

DLL errors are issued by DLL's own code and are defined in AVErrorsCodes.h.

The kind of code returned in “code” field is determined by the value of bit 0 of description[256]. A ‘1’ indicates DLL code error, a ‘0’ indicates OS system error.

## Error Handling Example

It is recommended that the user verifies the success of each call to SDK functions that have client number as an input parameter by subsequent call to GetLastClientError(number\_of\_client);

```
// declarations
// initialization
// create client
// main loop
// ...
ClientError* err = pGetLastClientError(number_of_client);
if(err->code > 0){
 if(err->description[255] & 1){
 // see AVErrorsCodes.h for identification
 // your code
 }
 else{
 // see MSDN into windows or error.h into linux
 // your code
 }
}
else{
 // fatal error - terminate, restart program
 // your code
}
```

## Error Codes defined in AVErrorsCodes.h

```
ZERO_POINTER = 1,
NO_ALLOCATED_MEMORY = 2,
```

|                               |       |
|-------------------------------|-------|
| BAD_SOCKET_ADDRESS            | = 3,  |
| TIMEOUT_ON_SOCKET             | = 4,  |
| READ_STRING_FROM_SOCKET       | = 5,  |
| TFTP_PROTOCOL                 | = 6,  |
| CAMERA_PARAMETER_OUT_OF_RANGE | = 7,  |
| UNKNOWN_CAMERA                | = 8,  |
| PARAMETER_NOT_SUPPORTED       | = 9,  |
| VALUE_OF_PARAMETER_UNKNOWN    | = 10, |
| UNKNOWN_ERROR                 | = 11, |
| CLIENT_ALREADY_EXISTS         | = 12, |
| CLIENT_OUT_OF_RANGE           | = 13, |
| CLIENT_DOES_NOT_EXIST         | = 14, |
| TFTP_MISSING_PACKETS          | = 15; |

Note that error `TFTP_MISSING_PACKETS` indicates that image has been received, but some packets might be missing, resulting in lost image segments.

## AV2000SDK.dll and AV2000SDK.so

### *List of Functions*

The shared libraries contain the following functions:

```
#define export_dll_function __declspec(dllexport)

// Client functions
extern "C" export_dll_function int CreateClient(int number);
extern "C" export_dll_function void DestroyClient(int number);
extern "C" export_dll_function unsigned MaxClients();
extern "C" export_dll_function const ClientError* const GetLastClientError(int number);
extern "C" export_dll_function int SetClientIp(int number, const char* ip);
extern "C" export_dll_function const char* GetClientIp(int number);
extern "C" export_dll_function void SetClientPort(int number, unsigned port);
extern "C" export_dll_function void SetClientTimeout(int number, unsigned value);
extern "C" export_dll_function unsigned GetClientTimeout(int number);
extern "C" export_dll_function unsigned GetClientPort(int number);
extern "C" export_dll_function int GetImage(int number, char** pBuffer, unsigned long* psize,
IMAGE_RESOLUTION resolution, float zoom, int dx, int dy);
extern "C" export_dll_function int GetImage2(int number, char** pBuffer, unsigned long* psize, unsigned
long* pcapacity, IMAGE_RESOLUTION resolution, float zoom, int dx, int dy);
extern "C" export_dll_function int GetWindowImage(int number, char** pData, unsigned long* size, unsigned
long* capacity, IMAGE_RESOLUTION, int left, int top, int width, int height);
extern "C" int export_dll_function STDCALL GetWindowImageQ(int number, char** pData, unsigned long* size,
unsigned long* capacity, IMAGE_RESOLUTION resolution, long IsPercent, long Aquality, int left, int top,
int width, int height);

extern "C" int export_dll_function STDCALL GetWindowImageQEx(int number, char** pData, unsigned long* size,
unsigned long* capacity, IMAGE_RESOLUTION, long IsPercent, long Aquality, int left, int top, int width, int
height, int codec, int streamId, int* Iframe);

extern "C" export_dll_function int GetDefaultImage(int number, char** pData, unsigned long* size, unsigned
long* capacity);
```

```

extern "C" int export_dll_function STDCALL GetDefaultImageEx(int number, char** pdata, unsigned long* size,
unsigned long* capacity, int codec, int streamId, int* Ifarme);

extern "C" export_dll_function int SetAV2000Register(int, unsigned char registr, unsigned char* value);
extern "C" export_dll_function int GetAV2000Register(int, unsigned char registr, unsigned char* value);
extern "C" export_dll_function int SetAV2000Parameter(int number, CAMERA_PARAMETER parameter, long* pvalue);
extern "C" export_dll_function int GetAV2000Parameter(int number, CAMERA_PARAMETER parameter, long* pvalue);
extern "C" export_dll_function int Permanently(int number);
extern "C" export_dll_function int FactoryDefault(int number);
extern "C" export_dll_function int UpdateVersion(int number);
extern "C" export_dll_function unsigned long Model(int);
extern "C" export_dll_function unsigned long Version(int number);
extern "C" export_dll_function unsigned long Revision(int number);
extern "C" export_dll_function unsigned long DayNight(int number);
extern "C" export_dll_function unsigned long Dome(int number);
extern "C" export_dll_function unsigned long Compact(int number);
extern "C" export_dll_function int SetCustomMode(int number, long* pknee_point, long* pmax_analog_gain,
long* pmax_knee_gain, long* pmax_exposure_time, long* pmax_digital_gain);
extern "C" export_dll_function int GetCustomMode(int number, long* pknee_point, long* pmax_analog_gain,
long* pmax_knee_gain, long* pmax_exposure_time, long* pmax_digital_gain);
extern "C" export_dll_function int IsBlackWhite(int number, int* pblack_white);
extern "C" export_dll_function int GetMac(AV2000Addr*);
extern "C" export_dll_function void SetClientBuffer(int number, char* buffer, unsigned long size);

typedef void (*PTR_Allocate)(char**, unsigned long*);
typedef void (*PTR_Deallocate)(char*);
typedef void (*PTR_Reinitd)(int number);

// Memory allocation support function
extern "C" export_dll_function void SetAllocateFunction(PTR_Allocate);
extern "C" export_dll_function void SetDeallocateFunction(PTR_Deallocate);
extern "C" export_dll_function void SetReinitdFunction(PTR_Reinitd);

// Camera detection and IP configuration functions
extern "C" export_dll_function int FindCameras(unsigned* number, unsigned timeout);
extern "C" export_dll_function int GetCameras(AV2000Addr*, unsigned* psize);
extern "C" export_dll_function int SetCameraIp(AV2000Addr*);
extern "C" export_dll_function const ClientError* const GetLastSetError();

```

```
extern "C" export_dll_function int CheckCamera(const char* ip);

// Auto-Iris functions
extern "C" export_dll_function int IrisPresent(int);
extern "C" export_dll_function int GetIrisStatus(int);

//Motion Detection Information
extern "C" export_dll_function const unsigned char* GetMotionArray(int number)

//Auxiliary IO Functions
extern "C" export_dll_function int SetAuxIO(int number, int value);
extern "C" export_dll_function int GetAuxIO(int number);
extern "C" export_dll_function int GetAuxOutStatus(int number);

//Single Capture Mode Functions
extern "C" export_dll_function int TriggerSingleCapture(int number);
extern "C" export_dll_function int GetSingleCapture(int number);
extern "C" export_dll_function int SetSingleCapture(int number, int value);
extern "C" export_dll_function int SetCalibrateFlash(int number);
extern "C" export_dll_function int GetCalibrationNumber(int number);

//EXIF CopyRight Strings Functions
extern "C" export_dll_function int InitializeCopyRightStrings(int, EXIF_STRING_ID, unsigned char*);
```

## Camera Communication Functions

For all functions “number” is the input argument specifying a client number. If a function returns an int, a positive value indicates a successful completion, value of 0 indicates an error during execution. The error code is accessed via `GetLastError()` returning a `ClientError` pointer.

- `void CreateClient(int number)`  
Creates an instance of AV2000 client. Returns 0 if success. Returns a positive value if recoverable error, see `AVErrorCodes.h` or negative if fatal error. The client number must be greater than 0 and less than `MaxClients()-1`.
- `void DestroyClient(int number)`  
Destroys the client and frees its memory, provided that the client exists. Otherwise no operation is performed.
- `unsigned MaxClients()`  
Returns maximum number of clients that can be created.
- `const ClientError* const GetLastError(int number)`  
Reports last error detected by the client.
- `void SetClientIp(int number, const char* ip)`  
Sets IP address of the client. The address must match the IP of a camera, where ip is specified as e.g. "192.168.254.10".
- `char* GetClientIp(int number)`  
Returns the client's IP address.
- `unsigned GetClientPort(int number)`  
Returns the client's port. Currently always returns 69, the number of TFTP port.
- `int GetImage(int number, unsigned char** buffer, unsigned long* psize, IMAGE_RESOLUTION resolution, float zoom, int dx, int dy)`  
Returns camera image in jpeg format. Note that for zoom = 1 the returned image size is determined by the values of `cpHEIGHT` and `cpWIDTH` with default size being smaller than maximum possible value in the case of AV3100, AV5100 and AV3130.
  - o `pbuffer` – pointer to the memory buffer containing the image (input/output parameter);
  - o `psize` – pointer to the size of received image;
  - o `resolution` – `imFULL`, `imHALF`, `imZOOM` as described above;
  - o `zoom` – determines the size of the window requested from the camera. Valid values are from 1.0 to 0.05. If zoom=1.0 and resolution=`imFULL` then the full image is requested. For zoom < 1.0, windows of smaller sizes are returned. For example, resolution=`imFULL` and zoom=0.25 returns the window of width 1600\*0.25=400 and height 1200\*0.25=300. The received image may not exactly match the requested due to camera restrictions.
  - o `dx, dy` – define the position of the window requested from the camera (for zoom < 1.0). The coordinates of the received window are given by:  
$$\begin{aligned} \text{Left} &= 1600 \cdot (1.0 - \text{zoom}) \cdot (50 - \text{dx}) / 100; & \text{Right} &= \text{Left} + 1600 \cdot \text{zoom}; \\ \text{Top} &= 1200 \cdot (1.0 - \text{zoom}) \cdot (50 - \text{dy}) / 100; & \text{Bottom} &= \text{Top} + 1200 \cdot \text{zoom}; \end{aligned}$$
  
Valid dx,dy values are from -50 to +50. (-50,-50) corresponds to lower left corner.  
Due to certain requirements imposed by the camera on the window alignment, the resulting window size and position may differ slightly from the requested values.
- `int GetImage2(int number, unsigned char** buffer, unsigned long* psize, unsigned long* pcapacity, IMAGE_RESOLUTION resolution, float zoom, int dx, int dy)`



Same as `GetImage` but has an added parameter `pcapacity` that returns the size of the buffer used for acquiring the image. Note that for `zoom = 1` the returned image size is determined by the values of `cpHEIGHT` and `cpWIDTH` with default size being smaller than maximum possible value in the case of AV3100, AV5100 and AV3130.

- o `pcapacity` is the full size of the image buffer while `psize` is the size of the image as above, wherein `psize` is always less or equal to `pcapacity`;

- `extern "C" export_dll_function int GetWindowImage(int number, char** pdata, unsigned long* size, unsigned long* capacity, IMAGE_RESOLUTION resolution, int left, int top, int width, int height),`  
Returns a rectangular sub-window of camera image;

- o `pdata`, `size`, `pcapacity` and `resolution` have the same meaning as in `GetImage()`;
- o `left`, `top`, `width` and `height` define the size of the image sub-window being requested, where `left` and `top` are in coordinates relative to `cpSENSOR_LEFT` and `cpSENSOR_HEIGHT`.  
Note: parameters `left` and `width` should be integer multiples of 32, while parameter `top` and `height` should be integer multiple of 16. Further, parameter `width` can not be less than 320 while parameter `height` can not be less than 240; For example, the following code results in transmitted image window that has the width and height of 1024 and has its left boundary at the sensor column 32 and top boundary at the sensor row 64:

```
SetAV2000Parameter(cpSENSOR_LEFT, 32);
SetAV2000Parameter(cpSENSOR_TOP, 64);
SetAV2000Parameter(cpSENSOR_WIDTH, 1024);
SetAV2000Parameter(cpSENSOR_HEIGHT, 1024);
char *data = new char[1000000];
unsigned long size = 1000000, capacity;
int left = 0, top = 0, width = 1024, height = 1024;
IMAGE_RESOLUTION res = imFULL;
GetWindowImage(1, &data, &size, &capacity, res, left, top, width, height)
```

- `extern "C" export_dll_function int GetWindowImageQ(int number, char** pdata, unsigned long* size, unsigned long* capacity, IMAGE_RESOLUTION resolution, long IsDoubleScan, long Aquality, int left, int top, int width, int height),`  
Returns a rectangular sub-window of camera image;

- o `pdata`, `size`, `pcapacity` and `resolution` have the same meaning as in `GetWindowImage()`;
- o `left`, `top`, `width` and `height` have the same meaning as in `GetWindowImage()`;
- o `IsDoubleScan`, 0 or 1.  
\* if this parameter is set to 1, this function will return an image that is AVAILABLE IMMEDIATELY. The same image could have been sent out multiple times, or it could be a new image just arrived in the buffer.  
\* if this parameter is set to 0, this function will return a NEW image. The image could be immediately available if the current buffer is never read before. Otherwise this function will wait until a new image is ready to be sent out;
- o `Aquality`, quality of requested image, 1~21, recommended value: 15.

- `extern "C" int export_dll_function STDCALL GetWindowImageQEx(int number, char** pdata, unsigned long* size, unsigned long* capacity, IMAGE_RESOLUTION, long IsPercent, long Aquality, int left, int top, int width, int height, int codec, int streamId, int* Iframe, int bitrate, int intra_period);`

Returns a rectangular sub-window of camera image. In comparison with `GetWindowImageQ` it has five additional parameters.

- o codec – is an input parameter which specifies codec type. 0 – MJPEG; 1 – H.264. Parameter value of 1 applies to camera models that support H.264 and end with “05”, for example “AV2105”.
- o streamId – is an input parameter which specifies stream identifier. MPEG codecs including H.264 codecs are context dependent (decoding of the current frame depends on the previous frame(s)). The stream is a sequence of frames of the same size which can be decoded sequentially by one instance of an MPEG decoder. Accordingly, streamId is a means to distinguish different streams from each other. Use unique streamId for each stream with a unique image size and/or frame rate. Value range of streamId is 0 through 65535. Camera supports 8 simultaneous streams. Each individual client must have a unique streamId. Parameter streamId will be ignored in case of JPEG codec.
- Iframe – is an input & output parameter. If Iframe is set to 1 the camera will return an Intra frame with a corresponding SPS and PPS as an IDR slice – so that the stream is decodable from this point. When opening a new stream (for example when changing the image size and/or frame rate) the Iframe parameter will be set automatically set to 1 regardless of the input value of Iframe. To minimize the stream size use Iframe = 1 as rarely as possible. The number of P-frames is set using SetAV2000Register with register=21, value=number of P-frames. The camera will return an Intra frame even if Iframe is set to 0 when the on-camera counter of P-frames fills up. To find out whether an Intra frame was received, check the value of Iframe after the function call. Parameter Iframe is ignored in case of JPEG codec type.
- bitrate – is an input parameter. This parameter is used to set up bitrate of the stream in kilobits per second. This parameter is only available for H.264 streams (ignored in case of JPEG stream). **If this parameter is non-zero then Aquality parameter will be ignored and camera will adjust quantization parameters toward desired bit rate.**
- intra\_period – is an input parameter. intra\_period should be equal to intra coded frame period. This parameter is used in rate control. This parameter is only available for H.264 stream( it is ignored in case of JPEG stream). If you are not use your own counter of inter coded frames and do not set up Iframe to 1( register 3:21 is used ) then you should use zero value. Let it be I – intra coded frame; P – inter coded frame. I P P P I - intra\_period must be 4; I I I I - intra\_period must be 1.
- extern "C" int **GetDefaultImage**(int number, char\*\* pdata, unsigned long\* size, unsigned long\* capacity)  
Returns a rectangular sub-window of full camera image, with the size, compression quality and resolution of returned of sub-window determined by the values of parameters cpRESOLUTION, cpQUALITY, cpREQUEST\_LEFT, cpREQUEST\_TOP, cpREQUEST\_WIDTH, cpREQUEST\_HEIGHT;  
  - o pdata, size, pcapacity have the same meaning as in GetImage();
  - o This function operates with cameras AV1300, AV2100 and AV3100, revision 5 and above, firmware version 52108 and above.
  - o For example, the following code results in transmitted image window that has the width and height of 1024 and has its left boundary at the full image column 32 and top boundary at the full image row 64:

```
SetAV2000Parameter(cpREQUEST_LEFT, 32);
SetAV2000Parameter(cpREQUEST_TOP, 64);
SetAV2000Parameter(cpREQUEST_WIDTH, 1024);
SetAV2000Parameter(cpREQUEST_HEIGHT, 1024);
char *data = new char[1000000];
unsigned long size = 1000000, capacity;
int left = 0, top = 0, width = 1024, height = 1024;
GetDefaultImage(1, &data, &size);
```

- `int SetAV2000Register(int number, unsigned char register, unsigned char* value)`  
Set AV2000 register to the value "value";
  - o register – camera register number – valid values are 0..255,
  - o value – register value, 2-element byte array, first element contains MSB, second element contains LSB.
- `int GetAV2000Register(int number, unsigned char register, unsigned char* value)`  
Read AV2000 register "register".
- `int SetAV2000Parameter(int number, CAMERA_PARAMETER parameter, long* pvalue)`  
Set a camera parameter described in enum CAMERA\_PARAMETER.
  - o pvalue – pointer to the value of the camera parameter (input)
- `int GetAV2000Parameter(int number, CAMERA_PARAMETER parameter, long* pvalue)`  
Returns the current value of the specified camera parameter.
- `int Permanently(int number)`  
Save current values of camera registers into camera non-volatile memory. The camera will use these settings after a power-off.

**NOTE: The use of this function is the ONLY way to store any parameters in the non-volatile memory. This function takes a few seconds to execute and it should not be called more than 20,000 times over camera lifetime, to prevent permanent damage to non-volatile memory.**

- `int FactoryDefault(int number)`  
Set camera and library parameters to their default values. Note that default values are loaded in the camera but are not saved permanently. To restore factory settings of the camera invoke function Permanently after invoking FactoryDefault.
- `int SetCustomMode(int number, long* pknee_point, long* pmax_analog_gain, long* pmax_knee_gain, long* pmax_exposure_time, long* pmax_digital_gain)`  
Set custom values for parameters of AE and AGC algorithm. Note that the use of this function is optional and for most users pre-defined values of cpCAMERA\_MODE will produce good results.
  - o pknee\_point – pointer to the value that specifies preferred exposure time. The camera will not increase exposure time above knee\_point until gain reaches the value pointed to by pmax\_knee\_gain; This parameter is specified in terms of the multiple of 10 ms increments for 50Hz setting, or 8.33 ms for 60Hz setting. The valid range is from 1 to 100.
  - o pmax\_analog\_gain – pointer to the value of maximum analog gain that will be used by the AGC algorithm; The valid range of this parameter is from 1 to 10;
  - o pmax\_knee\_gain – pointer to the value that specifies maximum gain (analog\*digital) that will be used by the AGC algorithm while the exposure time is equal to \*pknee\_point; This parameter is an integer value in the range from 2 to  $(*pmax\_analog\_gain) * (*pmax\_digital\_gain / 32)$
  - o pmax\_exposure\_time – pointer to the value of maximum exposure time that will be used by the AGC algorithm. This parameter is an integer value no greater than 100.
  - o pmax\_digital\_gain – pointer to the value that specifies maximum digital gain that will be used by the AGC algorithm. This parameter is an integer value in the range from 32 to 127, where 32 corresponds to gain of 1x, 64 corresponds to gain 2x, etc.

Example:

Setting `cpCAMERA_MODE = 1` is equivalent to using `SetCustomMode()` with `*pknee_point = 4`, `*pmax_analog_gain = 10`, `*pmax_knee_gain = 5`, `*pmax_exposure_time = 20` and `*pmax_digital_gain = 96`;

In this example, as the illumination decreases, camera will first increase exposure time to 40 ms, while maintaining gains close to unity, after that the camera will raise gain (in this case analog only) to 5x, after that the camera will increase exposure time to 200 ms, after that the camera will increase the analog gain to 10x and finally, the camera will increase digital gain to 3x.

- `void int GetCustomMode(int number, long* pknee_point, long* pmax_analog_gain, long* pmax_knee_gain, long* pmax_exposure_time, long* pmax_digital_gain)`

Returns current values of `*pknee_point`, `*pmax_analog_gain`, `*pmax_knee_gain`, `*pmax_exposure_time` and `*pmax_digital_gain`;

- `extern "C" export_dll_function int IsBlackWhite(int number, int* pblack_white)`

Returns color information about the last image obtained from AV3130 camera;

If `*pblack_white` is 0 then the last image was color image, otherwise the last received image was monochrome image. The monochrome image output by AV3130 appears as color image, as it has 3 color components, equal to each other. This function is meant to assist the user in switching decompressor parameters, as monochrome decompression is less cpu-intensive.

- `void SetClientBuffer(int number, char* buffer, unsigned long size)`

Sets image buffer used by the client to output the image.

- o `buffer` – pointer to the image buffer
- o `size` – size of the image buffer pointed to by “buffer”

- `typedef void (*PTR_Reinitd)(int number)`

Pointer to a function invoked during camera initialization or when client is connected or when the camera was powered off and on. The function is supplied by the application programmer and is called by the SDK DLL. “number” is the client number that identified camera power-on/off condition.

- `void SetReinitdFunction(PTR_Reinitd)`

Specifies the function that the client will use in the event of abrupt camera re-initialization (e.g. due to power interruption). This function has to be called prior to using the client.

- `const ClientError* const GetLastSetError()`

Obtain the last error that occurred after calling a camera usage, detection and IP configuration function. Acts identical to `GetLastClientError`

## Memory Allocation

- `typedef void (*PTR_Allocate)(char** pBuffer, unsigned long* psize)`

Pointer to a memory allocation function. The function has to be supplied by the application developer using AV SDK.

- `Pbuffer` – pointer to allocated memory, returned value
- `Psize` – input/output value, pointer to memory size requested by the DLL. After the memory allocation the application programmer should specify the actual value of memory that was allocated

If the allocated memory size is zero or less than requested the DLL will return an error with code 2, see `AVErrorCodes.h`.

For example,

```
// disallow memory allocation of sizes larger than 640K
Allocate(char** pbuf, unsigned long* psize)
{
 if(*psize > 640000){
 *pbuf = 0;
 return;
 }
}
```

The function pointed to by PTR\_Allocate is called in the following two cases:

- If the buffer size supplied by the user is insufficient for the image currently being acquired from the camera;
- When the user accesses camera registers;

• `typedef void (*PTR_Deallocate)(char* buffer)`

Pointer to a memory de-allocation function. The application programmer must supply this function, to be invoked by the DLL.

The function pointed to by PTR\_Deallocate is called in the following cases:

- Immediately after the user passes to the DLL the pointer to new image buffer (either using function pointed to by PTR\_Allocate or by using SetClientBuffer). In this case the function pointed to by PTR\_Deallocate is passed the pointer to the buffer that was supplied to the DLL **prior** to the buffer currently in use by the DLL;
- When DLL is unloaded from memory;

Note that calling SetClientBuffer does not lead to the invocation of the function pointed to by PTR\_Deallocate.

• `void SetAllocateFunction(PTR_Allocate)`

Specifies the function that the client will use to allocate memory. See usage notes and example below.

**NOTE: C# users are recommended to use default memory management to avoid pointer operations and unsafe compiling mode. Default can be activated by calling SetAllocateFunction(null).**

• `void SetDeallocateFunction(PTR_Deallocate)`

Specifies the function that the client will use to deallocate the memory.

1. Functions SetAllocateFunction and SetDeallocateFunction have to be called prior to using the client.

2. If allocated image buffer is too small to contain the arriving image, client calls the function PTR\_Allocate, using parameter size to indicate the requested buffer size. PTR\_Allocate should set the buffer pointer and allocate image buffer of equal or larger size, than requested, returning the actual allocated buffer size in the parameter size.

Example:

```
void OnAllocate(unsigned char** buffer, unsigned long* size)
{
 *size *= 2;
 *buffer = new unsigned char[size];
}
```

SetAllocateFunction(OnAllocate);

**NOTE: C# users are recommended to use default memory management to avoid pointer operations and unsafe compiling mode. Default is activated by calling SetDeallocateFunction(null).**

## Camera Detection and IP Configuration Functions

- `int FindCameras(unsigned* number, unsigned timeout)`  
Refresh list of cameras on the network. Number is both input and output parameter. As an input number points to number of re-tries. A re-try is attempted when the camera does not answer for some reason or the reply does not reach the source. As an output parameter (once FindCameras returns control) number is the pointer to the count of AV cameras found on the network. Timeout is the period of time between retries in milli-seconds. The function will wait for camera to reply during this time.
- `int GetCameras(AV2000Addr* paddr, unsigned* psize)`  
Obtain a list of detected cameras. FindCameras function must be called prior to using this function. Paddr points to an array of AV2000Addr structures. Pointer psize points to the size of array paddr. Its value is the number of structures, not size in bytes. Normally &number is assigned to psize where "number" is the same variable used by FindCameras function as output.
- `int SetCameraIp(AV2000Addr*)`  
Set camera IP address. To use the function fill out mac and ip arguments of AV2000Addr.
- `extern "C" export_dll_function int GetMac(AV2000Addr*)`  
Returns MAC address of the camera if IP address is known.

Example:

- ```
AV2000Addr addr;
// known IP address of the camera 169.254.1.10
addr.ip[0] = 169;
addr.ip[1] = 254;
addr.ip[2] = 1;
addr.ip[3] = 10;
GetMac(&addr); //addr.mac – contains MAC address of the camera;
```
- `int CheckCamera(const char* ip)`
Checks availability of a camera given its IP. "0" indicates that camera is not accessible. A positive value indicates success. SetAllocateFunction() and SetDeallocateFunction() must be invoked before using this function.
 - `int UpdateVersion(int number)`
Forces the client to read from the camera its firmware version and adapt its operation, so that backwards compatibility with older firmware versions is assured.
 - `unsigned long Model(int number)`
Returns camera model:
 - o 1300 for AV1300, AV1310
 - o 2000 for AV2000
 - o 2100 for AV2100, AV2110
 - o 3100 for AV3100, AV3110
 - o 3130 for AV3130
 - o 5100 for AV5100, AV5110
 - o 8360 for AV8360
 - o 8180 for AV8180
 - o 1305 for AV1305, AV1355
 - o 2105 for AV2105, AV2155
 - o 3105 for AV3105, AV3155
 - o 5105 for AV5105, AV5155
 - o 8365 for AV8365
 - o 8185 for AV8185
 - o 3135 for AV3135

- o 10005 for AV10005
- unsigned long **Version**(int number)
Reads firmware version of the camera.
- unsigned long **Revision**(int number)
Reads PCB revision of the camera.
- unsigned long **Dome**(int number)
Return 1 if camera model is
 - o AV1355
 - o AV2155
 - o AV3155
 - o AV5155Otherwise return 0
- unsigned long **Compact**(int number)
Return 1 if camera model is
 - o AV1310
 - o AV2110
 - o AV3110
 - o AV5110Otherwise return 0

Auto-Iris functions

- int **IrisPresent**(int number)
Returns 1 if auto-iris presents, 0 otherwise.

DayNight functions

- unsigned long **DayNight**(int number)
Returns 1 if mechanical IR switcher presents, 0 otherwise.

Camera parameters cpDAY_NIGHT_MODE, cpDAY_NIGHT_TRIGGER_NIGHT, and cpDAY_NIGHT_TRIGGER_DAY have been redefined to support single sensor cameras equipped with a day/night switch. These parameters can be set/read through **SetAV2000Parameter()** and **GetAV2000Parameter()** functions. Please read p.8 for details.

CopyRight Strings functions

- int **InitializeCopyRightStrings**(int number, EXIF_STRING_ID id, unsigned char* str);
Set camera make/software/copyright strings which will appear in JPEG header in EXIF format.

Example:

```
dll.pInitializeCopyRightStrings(1, CAMERA_MAKE_STRING, "Arecont Vision");  
dll.pInitializeCopyRightStrings(1, CAMERA_MODEL_STRING, "AV2100");  
dll.pInitializeCopyRightStrings(1, SOFTWARE_STRING, "AV SDK v2.6");  
dll.pInitializeCopyRightStrings(1, COPYRIGHT_STRING, "Arecont Vision");
```

CAMERA_MAKE_STRING, SOFTWARE_STRING, and COPYRIGHT_STRING accept up to 64 bytes, CAMERA_MODEL_STRING accepts up to 32 bytes.


SDK will automatically generate a datetime_picture_taken field for each image in form of YYYY:MM:DD HH:MM:SS. The datetime information can be viewed in Windows.

SDK will calculate a checksum for each image and embed the checksum in the JPEG header. This field is normally invisible. Arecont Vision will provide a standalone utility to verify if the checksum matches current image content.

Motion Detection

On-camera motion detection is now supported by all AV camera models. The unique design of AV cameras allows supporting highly accurate 64-zone motion detection. To provide accurate motion detection in low contrast and low light environments, EACH pixel of EACH frame is analyzed. The user can set size of motion detection zones (via cpMD_ZONE_SIZE), select the sensitivity to motion (via cpMD_LEVEL_THRESH), select the zones where the motion detection has to be suspended (via cpMD_MATRIX) and decide what size of the moving objects is of interest (via cpMD_DETAIL). In addition to retrieving motion detection information, the camera can also be configured to output images only if motion is detected (via cpMD_MODE).

On-camera motion detection algorithm uses $8 \times 8 = 64$ square zones to cover the camera's sensor rectangle*. The zones are numbered from 0 to 63 as shown in the figure below. Each zone comprises a number of fixed-sized sub-zones with each sub-zone containing 32×32 pixels. Parameter cpMD_ZONE_SIZE specifies how many sub-zones (in one direction) a zone comprises. Developers should calculate this parameter carefully so that the entire sensor rectangle can be covered by the zones.



*Camera's sensor rectangle is set using SDK functions SetAV2000Parameter() with parameter set {cpSENSOR_LEFT, cpSENSOR_TOP, cpSENSOR_WIDTH, cpSENSOR_HEIGHT} which are relative

to the physical sensor dimension. HOWEVER, the actual image size results from SDK functions such as `GetWindowImage()` DOES NOT necessarily equal the sensor rectangle if cropping is explicitly applied.

For example, AV2100 camera's default sensor dimension is 1600x1200. The best-fit zone size will be `cpMD_ZONE_SIZE = 7` so that $7 \times 32 \times 8 = 1792 \geq 1600$. AV5100 camera's default sensor dimension is 2560x1600. The best-fit zone size will be `cpMD_ZONE_SIZE = 11` so that $11 \times 32 \times 8 = 2816 \geq 2560$.

Important: users should keep it in mind that the total number of zones is always 64 (8 vertically and 8 horizontally). If the total zone size is larger than the actual image size, some zones may not correspond to the active pixel array. In that case some motion detection values are not meaningful and should be ignored.

For example, for AV1300 camera: if the image size is 1280x1024, then for `cpMD_ZONE_SIZE = 8` there are $5 \times 4 = 20$ active zones (3 zones after every 5 zones must be ignored during the `GetMotionArray` readout, as well as all zones after no. 31).

Parameter `cpMD_DETAIL` specifies at least how many sub-zones should contain motion for the zone in question to be considered as having motion. This parameter makes it possible to filter out motions caused by objects smaller than those to be detected.

To get information on the motion within each zone the user should use the function `GetMotionArray`:

- `const unsigned char* GetMotionArray(int number)` - returns an array of motion detection data; `number` -- is the client number, the value returned is the pointer to a 64-byte array where the 0th byte corresponds to the upper left corner of the image, 63rd byte corresponds to the bottom right corner. The byte value indicates the number of sub-zones (blocks of 32×32 pixels) within each zone where motion was detected. The sub-zone size is fixed and cannot be changed.

Setting `cpMD_MODE` to '1' will cause the camera to output image only at the presence of motion. To exclude some zones from motion detection the user can use the parameter `cpMD_MATRIX`. To specify the active zones the user should call `SetAV2000Parameter`, passing the pointer to an 8-byte array, where each byte corresponds to one horizontal row of zones, with MSB corresponding to the left margin of the image and the LSB to the right. Any bit set to 0 disables motion detection in the corresponding zone.


For example:

```
unsigned char arr[8];
    arr[0] = 0x7F;
    for(int i = 1; i < 8; i++)
        arr[i] = 0xFF;
    SetAV2000Parameter(1, cpMD_MATRIX, reinterpret_cast<long*>(arr));
```


The above example sets all zones as active, with the exception of the upper leftmost zone. Note the use of the cast to `(long*)`.

Binning Mode


"Binning mode" is a feature supported by AV10005 cameras. When enabled, the image sensor is sampled in such a way that adjacent 2×2 pixels are combined into one effective superpixel. In binning mode the "superpixel" has larger area for light integration, thus the low light sensitivity is enhanced, ideally by a factor of 4. The figures below illustrate the general concept of binning mode. On AV1005 cameras only Binning 2×2 is supported.



Binning 1x1 (none)
pixels: 144



Binning 2x2
pixels: 36



Binning 3x3
pixels: 16

In SDK two parameters `cpBIN_DAY` and `cpBIN_NIGHT` are introduced to support binning mode. Parameter `cpBIN_DAY` controls binning when camera is operating in day mode, and `cpBIN_NIGHT` controls binning when camera is operating in night mode. Since it is normally during night time that low light sensitivity becomes a concern, the factory default values are chosen to be `cpBIN_DAY=0` (disabled) and `cpBIN_NIGHT=1` (enabled).

Note that binning mode results in lower image resolution. If the image request is `imFULL` resolution and requested size is 3648x2752, the actual size of returned image will be 1824x1376 if binning is enabled. Similarly, if the image request is `imHALF` resolution and requested size is 3648x2752, the actual size of returned image will be 912x688 if binning is enabled.

1080p Mode

“1080p mode” is a feature supported by AV10005 cameras, controlled by parameter `cpBIN_1080P` with default value 0 (disabled). When enabled, the 10 megapixel image sensor on AV10005 operates at 30fps in 1920x1080 resolution. When switching from 10meg mode to 1080p mode, applications should handle carefully the change of sensor size: the requested image size should be properly trimmed and centered to fit within 1920x1080 resolution, do NOT use the same request sizes for 10meg resolution images.

When motion detection is enabled, applications should also change the `cpMD_ZONE_SIZE` parameter to proper values to reflect the change of sensor size. The default zone size for 10meg resolution is 15, while the suitable zone size for 1080p mode is 8.

Single Capture Mode

“Single Capture mode” support is temporarily removed from latest camera firmware releases. Users who want to continue using this feature may need to downgrade firmware to older versions.

When single capture is activated, the camera stops sending live video and enters an endless loop to check for external trigger events. The software that communicates with the camera must send image requests constantly and check whether the response from the camera contains image. When there is no event, the

camera responds to image requests with an empty data packet. When an event occurs, the camera responds to the most recent image request with the captured image.

Single capture function is primarily designed for low-light applications where an external flash is needed. When there is enough light, the camera automatically switches to a regular High Speed mode with short exposure time, about 1 ~ 2 ms, without triggering the flash.

To use the single capture function properly, the camera must be physically connected to an external trigger source (as input) and a flash (as output). Then the camera should go through a calibration process to setup a working environment. SDK users will use **SetCalibrateFlash()** function to initiate the calibration. The calibration process takes about 13 seconds, during which period the flash will be triggered 13 times. Once the calibration is done, users should check the result of calibration by calling **GetCalibrationNumber()** function. This function returns an integer resulting from the calibration. If the number is within **768 ~ 6144**, the calibration is successful, otherwise the calibration fails. For better image quality, one would expect the number to fall within **2000~3000** range. This number is under influence of the status of the iris. Closing the iris will cause the number to increase, and vice versa. Users may go through the calibration->adjusting iris->recalibration cycle for several times until the calibration result is satisfactory.

Once the calibration is done, the camera is ready to handle trigger events. During normal operation, there will be no image returned by functions like **GetImage2()**, **GetWindowImage()**, **GetDefaultImage()**, etc. In case of trigger, those functions will return a valid image. Users can judge the presence of image by the value of "size" parameter returned by those functions. If "size" is less than 1024, there is no image, otherwise the returned pointer points to a valid image.

For example:


```
int client = 1, enable = 1, ret = 0, ok=0, exit=0;
dll.pSetSingleCapture(client, enable);
dll.pSetCalibrateFlash(client);
Sleep(15000);
ret = dll.pGetCalibrationNumber(client);
ok = (ret > 768 && ret < 6144);

while(ok && !exit){
    GetWindowImage(client, buffer, size,...)
    if(size > 1024) // go on to process it
}
dll.pSetSingleCapture(client, enable=0);
```

Function **TriggerSingleCapture()** is to initiate single capture from software. Users should make sure the camera firmware support this feature before trying to use this function.

Auxiliary IO Functions

The auxiliary input and output are accessible from the back panel, as shown below. Both the input and the output are electrically isolated from the camera's internal electrical circuitry by general-purpose photo couplers. The input is further protected with a serial 250 Ohm resistor and a debouncing circuit.



Electrical characteristics:

		Min	Max
Input voltage (V) (measured between + and – terminals)	ON	2.9	6.3
	OFF	0	1.3
Output current (mA) (measured between + and – terminals)	ON	-	50
	Collector-Emitter Voltage (V)	0	80
	OFF	-	0.1

The use of Auxiliary IO functions through SDK involves three functions: **GetAuxIO()**, **SetAuxIO()** and **GetAuxOutStatus()**.

GetAuxIO() function read status of IN port.

SetAuxIO() function set status of OUT port.

GetAuxOutStatus() function reads back current status of OUT port.

For example:

```
//Get AuxIN status
long client = 1, ret = 0;
ret = dll.pGetAuxIO(client); //ret: 1 if voltage present, 0 otherwise

//Set AuxOUT status
long curr_status = dll.pGetAuxOutStatus(client);
long on_off = 1; //on_off: 1 for short-circuit, 0 for open circuit
dll.pSetAuxIO(client,on_off);
```

Caution: Starting from firmware version 64512 **GetAuxIO()** function reads AuxIN status from SDK local buffer instead of issuing new requests to camera. The purpose of this change is to improve efficiency. The SDK local buffer is updated when a new image arrives. For applications that do not request images until an

event is detected on AuxIN port, it is now necessary to request a small resolution image before calling **GetAuxIO()** function.

Panoramic Camera Functions

The overall SDK usage for the panoramic cameras (AV8360, AV8180, AV8365, AV8185) is similar to other camera models SDK usage with some specific differences.

- The differences are related to the internal camera functionality. Each of the camera's four image sensors may be exposed to different lighting conditions, and, as a result, the sensors may run asynchronously to each other, their images arriving at different times, and/or at a different rate. The image arrival times and/or their relative rate may change at any time depending on the current lighting conditions. In order to avoid any idle time waiting for a particular requested image to arrive, the camera's hardware sends images on a "first in, first out" basis. For these reasons, the application cannot explicitly specify the channel number (sensor number) within each individual image request: it will receive the next available image from the camera. For the same reason, neither can the application specify any other image parameter (such as resolution, brightness, quality, etc.) within an individual image request. To get images from the panoramic camera the SDK supports only `GetDefaultImage`, while various image parameters are set separately in advance (see below).
- There are three kinds of images that can be requested from the panoramic camera: full resolution image, decimated image (1/4 size), and a zoom window image. After the application receives an image from the camera using `GetDefaultImage()`, it must determine which channel has been received, and whether the image is a zoom window.
 - To determine which channel the image was received from, use `cpMS_NUMBER_OF_SENSOR`.
 - To determine whether the received image was a zoom window use `cpMS_IS_ZOOMED`, similarly to the above (except for parameters).
- The application can set various parameters individually for each channel, as well as enable/disable full resolution and/or zoom windows for each channel.
- When setting any parameter, specify which channel this setting applies to first, using `cpMS_NUMBER_OF_SENSOR`. For example, when setting brightness for channel 2, first set `cpMS_NUMBER_OF_SENSOR = 2`, then set brightness. The values for `cpMS_NUMBER_OF_SENSOR` range from 1 to 4.
- Image dimensions are set using `cpSENSOR_LEFT`, `cpSENSOR_TOP`, `cpSENSOR_WIDTH`, `cpSENSOR_HEIGHT`.
- A special camera mode is provided, in which each channel sends a full resolution image followed by four decimated images from all channels.. Typically, the decimated images are intended for displaying, while the full resolution images are intended for archival. It is enabled with `cpMS_QUAD_MODE`.
- Enabling/disabling camera channels is via `cpMS_CHANNEL_ENABLE`.
- Enabling/disabling full resolution channels is via `cpMS_FULL_RES_ENABLE`. The channels that are enabled via `cpMS_CHANNEL_ENABLE`, but not selected for full resolution via `cpMS_FULL_RES_ENABLE` send decimated images.
- Enabling/disabling zoom windows is via `cpMS_ZOOM_WIN_ENABLE`.

- In the panoramic camera motion detection is now supported. The usage of motion detection parameters (cpMD_ENABLED, cpMD_ZONE_SIZE, etc.) is similar to that of other models. The only tip is that cpMS_NUMBER_OF_SENSOR must be set properly before setting motion detection parameters.

For example:

```
// choose which sensor to set
long client = 1;
long num_of_sensor=1; //valid range 1~4
dll.pSetAV2000Parameter(client, cpMS_NUMBER_OF_SENSOR, &num_of_sensor);

//for the chosen sensor, enable/disable full resolution mode
long enable=1;
dll.pSetAV2000Parameter(client, cpMS_FULL_RES_ENABLE, &enable);

//for the chosen sensor, enable/disable that channel,
dll.pSetAV2000Parameter(client, cpMS_CHANNEL_ENABLE, &enable);

//request an image
dll.pGetDefaultImage(client, &Buffer, &Size, &Capacity);

//check the image comes from which sensor
if(Size > 1024)
dll.pGetAV2000Parameter(client, cpMS_NUMBER_OF_SENSOR, &num_of_sensor);

//check if it is zoom image, use only if zoom function is enabled
long is_zoom = 0;
dll.pGetAV2000Parameter(client, cpMS_IS_ZOOMED, &is_zoom);
```

To stream H.264 frames from AV8365/AV8185 cameras, the only option is to use GetDefaultImageEx() function defined as follows

```
extern "C" int GetDefaultImageEx(int number, char** pdata,
unsigned long* size, unsigned long* capacity, int codec, int streamId,
int* Iframe)
```

where;

- o pdata, size, capacity have the same meaning as in GetDefaultImage();
- o This function operates with cameras AV1300, AV2100 and AV3100, revision 5 and above, firmware version 52108 and above.

For example, the following code results in transmission of an H.264 frame:

```
int num_of_sensor = 0;
int is_zoom = 0;
if (bRequestH264Image)
{
    int Iframe = 0;
    int streamid = 1;
    ret = dll.pGetDefaultImageEx(1,
                                &pcImageBuffer, &iImageBufferSize,
                                &iImageBufferCapacity, H264_CODEC, streamid,
                                &Iframe);
}
```

```
dll.pGetAV2000Parameter(1, cpMS_NUMBER_OF_SENSOR, &num_of_sensor);
dll.pGetAV2000Parameter(1, cpMS_IS_ZOOMED, &is_zoom);
```

Note that the example code requests a P frame if possible. The actual frame type is determined by camera and returned in `Iframe`.

Examples

Arecont Vision provides a number of demo programs for different development tools and different model of cameras.

Development Tool	Package Name	Description
Borland C++ Builder 6.0	TestJpeg.rar	Support non-panoramic cameras, jpeg decompression, display and save to disk
	Test8360.rar	Support panoramic cameras, jpeg decompression, display and save to disk
Borland Delphi 7.0	DelphiRegualr	Support non-panoramic cameras, jpeg decompression, display and save to disk decompression uses Intel Jpeg Library (ijl15.dll)
Visual Studio 6.0 Console	Console.rar	Simple console application, find cameras and save image to disk
Visual Studio 6.0 MFC	MFC.rar	MFC example, jpeg decompression and display
Visual Studio 6.0 Win32	TestIJL.rar	Win32 application, display and save to disk, decompression uses Intel Jpeg Library (ijl11.dll)
Visual Studio 2005 C#	ApplicationRegular.rar	Support non-panoramic cameras, save to disk and display
	Application8360.rar	Support panoramic cameras, save to disk and display

DLL Usage Notes

Typical Usage

1. Create a client, `CreateClient()`
2. Set its IP, `SetClientIP()`
3. Receive camera version, `UpdateVersion()`
4. Main loop
 - a. Set camera parameters
 - b. Receive images, `GetImage()`
 - c. Etc.
5. Release client, `DestroyClient()`

Multi-Threading Applications

1. Calling `CreateClient()` and `DestroyClient()` from different threads requires the use of critical sections or other synchronization mechanisms.

2. Synchronization is also required if the client with the same number (ID) is called from different threads. Invoking functions of different instances of the client from different threads does not require critical sections/ synchronization.
3. To obtain maximum possible frame rate client should be able to acknowledge arriving from the camera packets as soon as possible. Therefore, whenever possible, client should have a higher priority than other threads.

Miscellaneous

1. All structures used in the library are aligned at 4 byte boundary
2. Certain network equipment is not designed to sustain high speed communications and may create transmission problems or slow FPS. In particular, many 3COM routers are found to cause high packet loss thus are not in the list of recommendation.

Maximum Image Sizes Supported By AV Cameras

(in pixels)

Camera Model	Default Width	Default Height	Max Width	Max Height
AV1300/1310/1305/1355	1280	1024	1280	1024
AV2100/2110/2105/2155	1600	1200	1600	1200
AV3100/3110/3105/3155	1920	1200	2048	1536
AV3130/3135 – color	1920	1200	2048	1536
AV3130/3135 – mono	1280	1024	1280	1024
AV5100/5110/5105/5155	2560	1600	2592	1944
AV10005	3648	2752	3648	2752
AV8360/8365	1600 *	1200 *	1600 *	1200 *
AV8180/8185	1600 *	1200 *	1600 *	1200 *

* : per channel, each AV8360/8180 has four independent channels

Revision History

Version 2.8.2

- Added DayNight support for panoramic cameras AV836X, AV818X with a DayNight switcher.
- Added support and documentation for camera model AV10005.
- Added Dome() function to identify AV1355/2155/3155/5155 models.
- Added Compact() function to identify AV1310/2110/3110/5110 models.
- Added comments for GetAuxIO() function.

Version 2.7.6

- Added support for camera model AV3135.
- Added GetAuxOutStatus() function.

- Fixed issue with cpLIGHTING and cpSHORT_EXPOSURES parameters for panoramic models.

Version 2.7.4

- Fixed an error in this document about cpDAY_NIGHT_MODE parameter.
- Fixed issue with reading/setting DayNight parameters, affecting single sensor DN models.
- Fixed issue with reading cpGAMMA parameter.
- Fixed issue with reading cpLIGHTING and cpSHORT_EXPOSURES parameters.

Version 2.7.3

- Added GetDefaultImageEx() function to support H.264 panoramic cameras.
- Added motion detection support for panoramic cameras.
- Added cpGAMMA parameter supported by all models (may need firmware/hardware update)
- Extended range of cpSHORT_EXPOSURES parameter to [1..80] with default 5
- Fixed an issue that AV51xx models lose 50/60Hz settings during camera initialization.

Version 2.6.5

- Fixed an issue that GetMac() function does not support panoramic cameras.
- Fixed an issue that FindCameras() function does not reliably find cameras in busy network due to extended packet delay.
- Fixed an issue that EXIF header only supports one camera model string.

Version 2.6.4

- Fixed an issue with panoramic cameras that AV2000SDK.dll allows setting iris related parameters, thus overwriting color balance registers.

Version 2.6.3

- Redefined DayNight camera parameters to support cameras equipped with a day/night IR switch.
- Added InitializeCopyRightStrings() to support custom information.
- Added invisible image fingerprint in JPEG header for data integrity purposes.

Version 2.6.2

- Added GetWindowImageQEx() to support H.264 cameras
- Added demo for H.264 developers using MS C++ and C#

Version 2.5.40

- Added TriggerSingleCapture()
- Modified GetWindowImageQ() to support in-request doublescan

Version 2.5.39

- Added GetSingleCapture(),SetSingleCapture(),SetCalibrateFlash(),GetCalibrationNumber()
- Added SetAuxIO() and GetAuxIO()
- Added GetWindowImageQ()
- Added demo for Borland Delphi and MS C#
- Fixed a typo related to the description of cpSHORT_EXPOSURES
- Rewrote motion detection section

Version 2.5.26

- Added HIGH_SPEED and MOON_LIGHT™ modes for cpCAMERA_MODE
- Added cpSHORT_EXPOSURES for specifying fixed shutter widths

Version 2.5.24

- Added AV8360 panoramic camera parameters and their description.
- Added parameters cpHEIGHT and cpWIDTH to allow obtaining larger than default images for AV3100, AV5100 and AV3130 when GetImage or GetImage2 is used.

Version 2.5.15

- Added motion detection parameter cpMD_DETAIL.

Version 2.5.14

- Fixed window size control for monochrome sensor of AV3130
- Added section on Motion Detection to the manual cpMD_DETAIL

Version 2.4.4

- Added support for the motion detection

Version 2.3.12

- Added checks for NULL pointers that might be erroneously passed by user to the SDK functions

- Commented out some motion detection related functions that are not yet used by the SDK but cause errors in some compilers

Version 2.3.11

- Modified default value of the parameter `cpMD_LEVEL_THRESH` (Rev5 cameras only)

Version 2.3.10

- Added error handling in the event of invocations of functions `Model(int)`, `Version(int)`, `Revision(int)` without prior call or failed call to `UpdateVersion(int)`. Prior to this modification the resulting exception was not handled, now 0 is returned.
- Added some functions for support of on-camera motion detection. These functions are not yet complete and can only be used for testing.

Version 2.3.6

- Put a safeguard to prevent the overflow of sensor exposure register for AV2100 (exposure value can not exceed 14 bits)

Version 2.3.5

- Modified `GetLastError` function to catch an error (return 0) in the event of a function call with non-existent client number.

Version 2.3.3

- Added parameters: `cpREQUESTED_BLOCK_SIZE` for camera with firmware versions of 52109 and above.

Version 2.3.1

- Added parameters: `cpSENSOR_BLACK_WHITE_LEFT`, `cpSENSOR_BLACK_WHITE_TOP`, `cpSENSOR_BLACK_WHITE_WIDTH`, `cpSENSOR_BLACK_WHITE_HEIGHT`, `cpPERCENT_IMAGE_RECTANGLE`, `cpREQUEST_LEFT`, `cpREQUEST_TOP`, `cpREQUEST_WIDTH`, `cpREQUEST_HEIGHT`, `cpQUALITY`, `cpRESOLUTION`, `cpSENSOR_LEFT`, `cpSENSOR_TOP`, `cpSENSOR_WIDTH`, `cpSENSOR_HEIGHT`
- Added functions: `GetWindowImage`, `GetMac` and `GetDefaultImage`.
- Added table of maximum image sizes for AV cameras;
- Added support for 2x packet size – 2904 bytes for camera versions 52109 and above;

Version 2.2.19

- Added parameters: `cpEXPOSURE_MODE`, `cpEXPOSURE_WINDOW_LEFT`, `cpEXPOSURE_WINDOW_TOP`, `cpEXPOSURE_WINDOW_WIDTH`, `cpEXPOSURE_WINDOW_HEIGHT`

Version 2.2.12

- Added support for AV3130

Version 2.2.9

- Corrected functions `SetCustomMode` and `GetCustomMode`, added `*pmax_digital_gain` parameter and expanded the description

Version 2.2.6

- Added functions `SetCustomMode` and `GetCustomMode`
- Added value 3 for `cpCAMERA_MODE`

Version 2.2.4

- Added error code `TFTP_MISSING_PACKETS` to `AVErrorCodes.h`
- Expanded description of functions pointed to by `PTR_ALLOCATE` and `PTR_DEALLOCATE`

Version 2.2.0

- Added function `GetImage2`

Version 2.0.14b

- `cpBRIGHTNESS` is -99..99

Version 2.0.14

- Corrected `cpCAMERA_MODE` values

Version 2.0.13

- SDK removed `cpIRIS_REPOSITION_ENABLED` (merged into `cpIRIS_ENABLED`)

Version 2.0.12

- SDK fixed `cpIRIS_ENABLED` setting
- SDK changed `cpIRIS_REPOSITION_F_STOPS` range to 1..15

- SDK changed cpIRIS_REPOSITION_F_STOPS_MIN range to 1..15
- SDK enlarged cpBRIGHTNESS range to -75..75
- SDK added cpAUTO_EXPOSITION, 0..1
- SDK changed some defaults

Version 2.0.11c

- Compression quality settings limited to 21

Version 2.0.11b

- Zoom description in GetImage()

Version 2.0.11

- Added int CheckCamera()
- Added cpDAY_NIGHT*

Version 2.0.10

- Added enum IRIS_STATUS
- Added GetIrisStatus()
- Updated cpROLL for camera versions before 51719
- Reduced camera communication access delay

Version 2.0.9g

- Added parameter support for camera version 50412

Version 2.0.9f

- cpIRIS_ENABLED, cpIRIS_REPOSITION_ENABLED values are 0 and non-zero

Version 2.0.9d

- IRIS_SPEED is 1..255, not 0..255

Version 2.0.9c

- Corrected formula and defaults for cpIRIS_REPOSITION_PERIOD, cpIRIS_REPOSITION_STABLE_PERIOD. cpDOUBLESCAN default is 0

Version 2.0.9b

- cpIRIS* attributes

Version 2.0.9

- Support storage of saturation, sharpness and rotation defaults on the camera. Firmware 50412 and later

Version 2.0.8

- Added FactoryDefault()
- Fixed GetAV2000Parameter for cpROLL, cpLIGHTING and cpCAMERA_MODE

Version 1.34

- SetAV2000Parameter() example in sample.cpp

Version 1.33

- Fixed description of ranges of brightness, blue/red adjustment, quality full, half, zoom
- CreateClient() changed, returns 0 when no error
- Added MaxClients()

Version 1.22

- Added AVErrors.h
- Added SetClientTimeout()
- Added GetClientTimeout()
- Example to limit memory allocation size